

Infragistics Windows Forms 13.2 Service Release Notes

– April 2014

 **INFRAGISTICS™**
WINDOWS FORMS



Add complete usability and extreme functionality to your next desktop application with the depth and breadth our Windows Forms UI controls. Infragistics Windows Forms continues to make strides in user experience with the latest Windows® 7, Windows® 8, Office® 2010 and Office® 2013 styles.

Installation

Downloading	Download Infragistics Windows Forms here.
--------------------	---

What's Changed

Components	Product Impact	Description
Infragistics Excel	Bug Fix	Exporting an image to an XLS file causes NullReferenceException. Notes: Fixed an issue in the Excel library where saving an xls file containing a group with a single shape in it caused a NullReferenceException.
Infragistics Excel	Bug Fix	Loading excel file with formulas containing longer than 256 characters caused FormulaParseException. Notes: Fixed an issue with the Excel library where string literals with newlines contained in formulas were not saved/loaded correctly in the XLSX format.
Infragistics Excel	Bug Fix	The euro symbol is replaced with a dollar sign when a Workbook file is saved. Notes: Fixed an issue in the Excel library when certain currency symbols in format strings were not saved/loaded correctly.
WinChart	Bug Fix	The Text primitive's FontColor property does not allow overriding it.
WinChart	Bug Fix	The Detach method is not being called from the Dispose method that causes memory leak.
WinEditors	Bug Fix	A ReadOnly property was not defined in EditorButtonControlBase class.

WinMaskedEdit	Bug Fix	Using the InputMask character “&” accepts a Japanese character.
WinNumericEditor	Bug Fix	The Control's height fails to change based on the font size specified in AppStylist.
WinExplorerBar	Bug Fix	Disposing of the scrollbar in the UltraExplorerBar causes memory Leak.
WinGanttView	Bug Fix	An unhandled exception occurs when clicking the horizontal scroll thumb after switching DisplayAreas property from GridOnly to GridAndTimeLine.
WinGrid	Bug Fix	An "Object reference not set to an instance of an object" error is raised with the cell's CharacterCasing property is set to "CharacterCasing.Upper".
WinGrid	Bug Fix	The text in the designer labels is cut off, when the text is scaled to 200% or more.
WinGrid	Bug Fix	UltraCombo/UltraComboEditor controls do not allow selecting two-word values when the control is embedded into a string column.
WinGrid	Bug Fix	RowFilter icon is aligned with ImageHAling = Center / ImageHAling = Right.
WinGrid	Bug Fix	UltraGrid does not take fixed columns into account when scrolling horizontally after area of the scrollbar outside of the thumb or arrows is clicked.
WinGrid	Bug Fix	Column autosizing is incorrect with summary, and image in summary row.
WinGrid	Bug Fix	When DeferredCalculationsEnabled is true, out of view cells are not calculated when they are scrolled into view using the horizontal scrollbar.
WinGrid	Bug Fix	Opening a Form with UltraGrid in Visual Studio designer and closing it prompts to save changes while no changes were applied.
WinListView	Bug Fix	An error occurs when clicking on a list item that is being removed.
WinPrintPreviewDialog	Bug Fix	Printing in Portrait Mode causes some rows to be excluded from the grid view due to margin calculation.
WinRadialMenu	Bug Fix	AlphaLevel setting had no effect on "MenuSettings.Appearance.AlphaLevel".
WinDayView	Bug Fix	Appointment border was missing in UltraDayView.
WinSchedulePrintDocument	Bug Fix	The month on the printed document is a different month on the preview.
WinToolbarsManager	Bug Fix	The StateButtonTool doesn't support mnemonics when its ToolBarDisplayStyle is set to Glyph.
WinToolbarsManager	Bug Fix	The "TextHAligment.Left" property setting fails to align the text of the MaskEditTool and SateButtonTool on the same X coordinate.
WinToolbarsManager	Bug Fix	Pressing on Combo tools with touch-enabled mode behaves as a right-click (contrext menu) instead of a drop down list.

WinTree

Bug Fix

Adding a node to the Tree causes an "ArgumentOutOfRangeException".